

D3.3 Software Installation Manual

Due date: 1/10/2023 Submission Date: 31/07/2023

Start date of project: 01/07/2023 Duration: 36 months

Lead organisation for this deliverable: Carnegie Mellon University Africa

Responsible Person: CSSR4Africa Team Revision: 1.1

	Project funded by the African Engineering and Technology Network (Afretec) Inclusive Digital Transformation Research Grant Programme			
	Dissemination Level			
PU	Public	PU		
PP	Restricted to other programme participants (including Afretec Administration)			
RE	Restricted to a group specified by the consortium (including Afretec Administration)			
CO	Confidential, only for members of the consortium (including Afretec Administration)			



Contents

Ex			3
1	Intr	duction	4
2	Setti	ng up the Development Environment	4
	2.1	Prerequisite	4
	2.2	Setting up the Development Environment for the Physical Robot	5
		2.2.1 Installing and Configuring the C++ NAOqi SDK	5
		2.2.2 Installing NAOqi Driver and ROS Packages	6
		2.2.3 Bring up Pepper	7
	2.3	Setting up the Development Environment for the Gazebo Simulator	9
		2.3.1 Install Docker Using the Apt Repository	9
		2.3.2 Install the Pepper Gazebo Simulator	10
		2.3.3 Driving the Pepper Robot in the Simulator	10
3	Inst	lling and Running the CSSR4Africa Software	13
	3.1	Installing the CSSR4Africa Software	13
	3.2	Running the CSSR4Africa Software	13
		3.2.1 The Pepper Diagnostic Routine Test	13
Pr	incip	l Contributors	16
Do	ocume	nt History	17



Executive Summary

Deliverable D3.3 serves as a comprehensive installation manual for the Culturally Sensitive Social Robotics for Africa (CSSR4Africa) project. The manual will be continually updated as a living document to ensure it reflects the current capabilities of the system. The objective of this task is to document the process of installing and executing the required software components to instantiate the CSSR4Africa system. It provides step-by-step instructions for setting up the development environment and controlling the Pepper robot in both physical and simulated environments.

Date: 31/07/2023 Page 3



1 Introduction

This Deliverable, D3.3: Software Installation Manual documents the process for the installation and execution of the software required to instantiate all or part of the CSSR4Africa system and run the unit, integration, and system tests. This installation manual assumes the system has a native Ubuntu 18.04 operating system. It was tested on a computer device with a storage of 512GB, 16GB of RAM, and 4 Intel CPU cores.

The installation is divided into 2 main sections. Section 2, is for setting up the development environment for the physical robot and the Gazebo simulator. Section 2 first goes through a prerequisite setup that is needed for both the physical robot and Gazebo simulator environments and proceeds with corresponding installation steps. Section 3, will discuss installing and running of the CSSR4Africa software.

2 Setting up the Development Environment

This section provides step-by-step instructions for installing a set of software packages required to control the physical Pepper robot and the robot in the Gazebo simulator. Open a new terminal (ctrl + shift + t) and type the following commands carefully.

2.1 Prerequisite

The prerequisite for setting up the development environment for both the physical robot and the simulator is installing ROS Melodic. The following instructions are followed to install ROS melodic.

1. Setup the computer to accept software from packages.ros.org.

```
sudo sh -c 'echo "deb http://packages.ros.org/ros/ubuntu \
$(lsb_release -sc) main" > /etc/apt/sources.list.d/ros-latest.list'
```

2. Install curl.

```
sudo apt install curl
```

3. Setup your keys.

```
curl -s https://raw.githubusercontent.com/ros/rosdistro/\
master/ros.asc | sudo apt-key add -
```

4. Update Debian package index.

```
sudo apt update
```

5. Install ROS Melodic with the default configurations.

```
sudo apt install ros-melodic-desktop-full
```

6. Make ROS environment variables automatically added every time a new shell is launched.

```
echo "source /opt/ros/melodic/setup.bash" >> $HOME/.bashrc
source $HOME/.bashrc
```

Date: 31/07/2023 Page 4
Version: No 1.1



Setting up the Development Environment for the Physical Robot

2.2.1 Installing and Configuring the C++ NAOqi SDK

NAOqi serves as the main software responsible for running and controlling the Pepper robot. To control Pepper with ROS, NAOqi needs to be installed, and a suitable ROS driver must be found to enable communication between the two software platforms. The NAOqi Framework, being a crosslanguage programming framework utilized for programming Pepper, allows programming the robot using both C++ and Python languages. For the development of the bridge, the NAOqi C++ SDK needs to be installed, and the following steps detail the installation process.

1. Check compiler version.

A GCC compiler version 4.8.2 or higher is required. On most Ubuntu distributions, it is installed by default. Check the GCC version by typing the following command:

```
gcc -v
```

2. Install pip.

If you don't have pip installed on your machine, please run the code below.

```
sudo apt install python-pip
```

3. Install qbuild.

qbuild is used to create a cross-platform executable.

```
pip install qibuild --user
```

4. Update the path environment variable.

```
# to load qBuild when your shell starts
PATH=$PATH:$HOME/.local/bin
```

5. Configure qBuild.

```
qibuild config --wizard
# Input 1 and hit enter (1 Unix Makefiles (default))
# Input 1 and enter (1 None (default))
```

6. Make a directory to work in.

```
mkdir myworktree && cd myworktree
```

7. Download the NAOqi-SDK.

```
wget -P $HOME/Downloads/ https://community-static.aldebaran.com/\
resources/2.5.10/NAOqi%20SDK/naoqi-sdk-2.5.7.1-linux64.tar.qz
```

8. Go to the download folder and extract the downloaded file.

```
1 cd $HOME/Downloads
2 tar -xvzf naoqi-sdk-2.5.7.1-linux64.tar.gz
```

Date: 31/07/2023 Page 5



9. Create a toolchain.

```
qitoolchain create mytoolchain \ $HOME/Downloads/naoqi-sdk-2.5.7.1-linux64/toolchain.xml
```

10. Go to the myworktree directory and configure the SDK.

```
cd $HOME/myworktree
qibuild init
qibuild add-config myconfig -t mytoolchain --default
```

2.2.2 Installing NAOqi Driver and ROS Packages

The NAOqi driver is a module that provides some bridge capabilities. It publishes sensory data, and the robot position (Pepper in our case) and enables ROS to call part of the NAOqi API. The easiest way is to install it with the apt package tool used to install software on Ubuntu. Installing the driver through the apt will not provide all the packages needed to communicate with the robot through ROS. For example, the **naoqi_dcm_driver**, is the package controlling the robot's actuators. Thus, the remaining packages were compiled from their sources through catkin make. This requires cloning the official sources code from GitHub. Below are the steps to follow.

```
# Install the NAOgi driver
2 sudo apt-get install ros-.*-naoqi-driver
4 # Create ROS workspace
5 mkdir -p $HOME/workspace/ros/src
7 # Move to workspace directory
8 cd $HOME/workspace/ros/src
10 # Install Git
n sudo apt install git
# Clone NAOqi DCM driver repository
14 git clone https://github.com/ros-naoqi/naoqi_dcm_driver.git
15
# Clone Pepper DCM driver repository
17 git clone https://github.com/ros-naoqi/pepper_dcm_robot.git
# Clone Pepper virtual repository
20 git clone https://github.com/ros-naoqi/pepper_virtual.git
22 # Clone NAOqi driver repository
23 git clone https://github.com/ros-naoqi/naoqi_driver.git
25 # Clone Pepper robot repository
26 git clone https://github.com/ros-naoqi/pepper_robot.git
28 # Clone Pepper moveit config repository
29 git clone https://github.com/ros-naoqi/pepper_moveit_config.git
31 # Build the repository
32 cd .. && catkin_make
```



```
33 # Add the workspace to your ROS environment by sourcing the setup file in
      devel folder
34 source devel/setup.bash
36 # Add the setup to your .bashrc file so that you don't have to do this
     every time you open a new terminal
37 echo "source $HOME/workspace/ros/devel/setup.bash" >> $HOME/.bashrc
38
39 # Install additional packages
40 sudo apt-get install ros-melodic-joint-trajectory-controller
42 sudo apt-get install ros-melodic-ros-controllers
43
44 sudo apt-get install ros-melodic-pepper-meshes
45 # When configuring window opens up, you may agree to the license terms
     using the right/left arrow key and select <ok> and hit enter, and then
      select <Yes> to accept the terms and press enter
47 # Install rosdep
48 sudo pip install -U rosdep
49 sudo rosdep init
50 rosdep update
52 rosdep install --from-paths src --ignore-src -r -y
```

You might encounter the following error when launching the driver in the section 2.2.3.



terminate called after throwing an instance of 'qi::FutureUserException'what(): Can't find service: ROS-Driver-Audio

Currently, the cause of the issue and its solution remain unidentified. As a temporary workaround, disable the audio service. To deactivate the Audio Service, access the boot config file using the below command and set the audio key to "false". After making the change, remember to save the file.

```
sudo nano $HOME/workspace/ros/src/naoqi_driver/share/boot_config.json
```

The audio service is being deactivated as a temporary workaround to ensure the functionality of the NAOqi driver. It is important to note that this action will result in the microphone not working. Despite exploring various alternatives, the problem persisted, leaving with no other viable solutions currently covered in this manual. The upcoming version of the software installation manual will address this issue and provide alternative solutions to resolve the microphone functionality along with the NAOqi driver's operation.

2.2.3 Bring up Pepper

To establish communication between the computer device and the Pepper robot, the IP address of the computer device and its network interface name, and the IP address of the Pepper robot are needed. Below are the steps to find this information. First, make sure the Pepper robot and computer device are on the same network.

Date: 31/07/2023 Page 7



1. IP address identification of the computer

In order to find the IP address of the computer device, open a new terminal and execute the following commands.

(a) Install network tool (if not installed).

```
sudo apt install net-tools
```

(b) Identify network ip and interface name.

ifconfig

```
10:19:58 yohanneh@CSSR4A-Robotics-Lab:~
          flags=4099<UP,BROADCAST,MULTICAST> mtu 1500
        inet 172.17.0.1 netmask 255.255.0.0 broadcast 172.17.255.255
        inet6 fe80::42:63ff:fe97:aef4 prefixlen 64 scopeid 0x20<link>
        ether 02:42:63:97:ae:f4 txqueuelen 0 (Ethernet)
        RX packets 14799 bytes 890282 (890.2 KB)
        RX errors 0 dropped 0 overruns 0 frame 0
        TX packets 23466 bytes 46389487 (46.3 MB)
         TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
ens160
        flags=4163<UP.BROADCAST,RUNNING,MULTICAST>
        inet 172.29.111.229 netmask 255.255.0 broadcast 172.29.111.255
inet6 fe80::250:56ff:fe8b:50b0 prefixlen 64 scopeid 0x20link>
ether 00:50:56:8b:50:b0 txqueuelen 1000 (Ethernet)
        RX packets 11544145 bytes 5387799739 (5.3 GB)
        RX errors 0 dropped 0 overruns 0 frame 0
         TX packets 7859783 bytes 19733006740 (19.7 GB)
         TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
lo: flags=73<UP,LOOPBACK,RUNNING> mtu 65536
        inet 127.0.0.1 netmask 255.0.0.0
        inet6 ::1 prefixlen 128 scopeid 0x10<host>
        loop txqueuelen 1000 (Local Loopback)
RX packets 2204209 bytes 304665921 (304.6 MB)
        RX errors 0 dropped 0 overruns 0 frame 0
TX packets 2204209 bytes 304665921 (304.6 MB)
         TX errors 0 dropped 0 overruns 0 carrier 0 collisions 0
l0:20:01 yohanneh@CSSR4A-Robotics-Lab:~ $
```

Figure 1: "ifconfig" command output: Network interface name and IP address.

Upon executing the "ifconfig" command, the output will display information similar to the illustration shown in Figure 1. Take note of the network interface name along with its corresponding IP address as shown in the output. This IP address will be passed as a value for roscore_ip argument later in the document.

2. IP address identification of the Pepper robot

To find the IP address the Pepper Robot, ensure the robot is powered on and connected to the network. Usually while the Pepper Robot is booting it says, "Hello, I'm Pepper, my internet address is $< robot_ip >$ (for example, 172.29.111.230)" or in case you missed it, press the chest button once and make note of that IP address. This IP address will be passed as a value for robot_ip argument.

Date: 31/07/2023 Page 8



Using the above IP address of the robot, the IP address and the network interface name of the computer device, the following instruction will bring Pepper up over ROS and the NAOqi driver will be launched. Below are the instructions to follow:

1. Bring up the Pepper robot, assuming the robot is turned on.

```
roslaunch pepper_dcm_bringup pepper_bringup.launch \
robot_ip:=172.29.111.230 roscore_ip:=172.29.111.229 \
network_interface:=ens160
```

2. Launch the NAOqi driver.

```
roslaunch naoqi_driver naoqi_driver.launch nao_ip:=172.29.111.230 \
roscore_ip:=172.29.111.249 network_interface:=ens160
```

2.3 Setting up the Development Environment for the Gazebo Simulator

Section 2.2 assumes access to a physical Pepper robot. However, circumstances may arise where testing software without the physical robot becomes necessary. In such cases, a simulator can serve as an alternative. This section explains how to control the Pepper robot within a Gazebo simulator. The simulation is based on an open-source Pepper ROS environment developed by Sam Pfeiffer and Finn Rietz.¹

2.3.1 Install Docker Using the Apt Repository

Below are a set of instructions to install the Docker engine on Ubuntu.²

1. Make sure to uninstall any conflicting packages.

```
for pkg in docker.io docker-doc docker-compose podman-docker \
containerd runc; do sudo apt-get remove $pkg; done
```

2. Update the apt package index and install packages to allow apt to use a repository over HTTP.

```
sudo apt-get update sudo apt-get install ca-certificates curl gnupg
```

3. Add Docker's official GPG key.

```
sudo install -m 0755 -d /etc/apt/keyrings

curl -fsSL https://download.docker.com/linux/ubuntu/gpg | sudo gpg \
--dearmor -o /etc/apt/keyrings/docker.gpg

sudo chmod a+r /etc/apt/keyrings/docker.gpg
```

Date: 31/07/2023 Page 9
Version: No 1.1

¹The Pepper ROS simulator is available on the following link: https://github.com/frietz58

²This is a subset of the official documentation available at https://docs.docker.com/engine/install/ubuntu/. Please refer to the commands in this link in case of any difficulties replicating the commands in this section.



4. Use the following command to set up the repository.

```
echo \
"deb [arch="$(dpkg --print-architecture)" \
signed-by=/etc/apt/keyrings/docker.gpg] \
https://download.docker.com/linux/ubuntu \
"$(. /etc/os-release && echo "$VERSION_CODENAME")" stable" | \
sudo tee /etc/apt/sources.list.d/docker.list > /dev/null
```

5. Update the apt package index.

```
sudo apt-get update
```

6. Install Docker Engine, container, and Docker Compose.

```
sudo apt-get install docker-ce docker-ce-cli containerd.io \
docker-buildx-plugin docker-compose-plugin
```

7. Verify that the Docker Engine installation is successful by running the hello-world image.

```
sudo docker run hello-world
```

This command downloads a test image and runs it in a container. When the container runs, it prints a confirmation message and exits.

2.3.2 Install the Pepper Gazebo Simulator

1. Go to home directory and clone pepper_virtual GitHub repository.

```
cd $HOME && git clone https://github.com/frietz58/pepper_virtual
```

2. Move to the pepper_virtual directory.

```
cd pepper_virtual
```

3. Build image from provided Dockerfile.

```
sudo docker build -t awesome-pepper-sim .
```

4. Allow Docker to open GUIs on the surrounding OS.

```
xhost +local:root
```

5. Run the Docker container.

```
sudo docker run -it -v /tmp/.X11-unix:/tmp/.X11-unix -e \
DISPLAY=unix$DISPLAY awesome-pepper-sim
```

6. Start the Gazebo simulation.

```
roslaunch pepper_gazebo_plugin \
pepper_gazebo_plugin_in_office_CPU.launch
```

If everything goes well, your simulation environment should be similar to the figure 2.






Figure 2: Pepper Gazebo simulation environment.

Driving the Pepper Robot in the Simulator

In this section, the Pepper robot is driven in the simulation environment using the rqt GUI joint trajectory controller application using the following instructions:

1. Open a new terminal, run the command below and take note of the returned container ID.

```
sudo docker ps
```

2. Attach a new shell to the container with the ID obtained from running the previous command.

```
sudo docker exec -it <CONTAINER-ID> bash
```

3. Start rqt steering with Pepper's base topic.

```
rosrun rqt_robot_steering rqt_robot_steering \
--default_topic:=/pepper/cmd_vel
```

4. Open a new terminal and start joint trajectory controller to drive Pepper robot in the simulator.

```
sudo docker exec -it <CONTAINER-ID> bash
rosrun rqt_joint_trajectory_controller \
rqt_joint_trajectory_controller
```

Date: 31/07/2023 Page 11



Upon initiating the joint trajectory controller, a user interface resembling Figure 3 will be displayed. To steer the robot, the rqt_robot_steering GUI can be utilized, where two sliders are available for adjusting velocity and steering. Additionally, the rqt_joint_trajectory_controller provides a GUI for the joint controller, allowing movement control through sliders corresponding to the available joints. For instance, the pelvis joints, HipPitch and HipRoll, can be controlled using this interface.




Figure 3: Joint trajectory controller.



3 Installing and Running the CSSR4Africa Software

3.1 Installing the CSSR4Africa Software


This section will guide you through the installation process of the CSSR4Africa software in the source directory of the workspace. The outlined steps for installing the CSSR4Africa software are as follows:

```
# move to the source directory of the workspace
cd $HOME/workspace/ros/src

# clone the CSSR4Africa software from the GitHub repository
git clone https://github.com/cssr4africa/cssr4africa.git

# build the source files
cd .. && catkin_make
```

Upon completing the installation above, the **src** folder within the development environment's workspace will contain the CSS4Africa software meta-package and all the packages used to enable communication between ROS and NAOqi. Below is the directory structure of the workspace for reference.



3.2 Running the CSSR4Africa Software

In this section, the execution of the unit, integration, and system tests of the CSSR4Africa software packages for the physical robot and the robot simulator will be presented.

3.2.1 The Pepper Diagnostic Routine Test

The pepper_diagnostic_routines package contains the source files that have been written to perform the unit tests to evaluate the functionality and performance of sensors and actuators on the physical robot and the robot simulator.

Date: 31/07/2023 Page 13



3.2.1.1 The Pepper Diagnostic Routine Test on the Physical Robot

In this section, the Pepper robot sensors and actuators will undergo unit tests. The process begins with running the 'pepper_diagnostic_routines' package and the NAOqi driver. Each sensor and actuator will be tested, and the expected output for each test will be specified.

1. Open a new terminal and launch the pepper diagnostic routines. Please replace the variables robot_ip, roscore_ip, and network_interface_name with the values obtained from the section 2.2.3.

```
roslaunch pepper_diagnostic_routines diagnostics.launch \
robot_ip:=<robot_ip> roscore_ip:=<roscore_ip> \
network_interface:=<network_interface_name>
```

2. Open a second terminal and launch the NAOqi driver. Please replace the variables robot_ip, roscore_ip, and network_interface_name with the values obtained from the section 2.2.3.

```
roslaunch naoqi_driver naoqi_driver.launch nao_ip:=<robot_ip> \
roscore_ip:=<roscore_ip> network_interface:=<network_interface_name>
```

- 3. Open a third terminal and perform the following tests.
 - (a) Test the back sonar

Expected output: The test outputs the back sonar sensor frame ID, its field view, the minimum and maximum distance range it can measure.

```
rosrun pepper_diagnostic_routines back_sonar
```

(b) Test the bottom camera

Expected output: The test displays a RGB image of the scene captured by the camera.

```
rosrun pepper_diagnostic_routines bottom_camera
```

(c) Test the depth camera

Expected output: The test displays a gray scale image of the scene captured by the camera.

```
rosrun pepper_diagnostic_routines depth_camera
```

(d) Test the front camera

Expected output: The test displays a RGB image of the scene captured by the camera.

```
rosrun pepper_diagnostic_routines front_camera
```

(e) Test the hand touch

Expected output: The test outputs which hand (right or left) has been touched and the state of the hands (released or touched).

Date: 31/07/2023 Page 14 Version: No 1.1



rosrun pepper_diagnostic_routines handTouch

(f) Test the laser

Expected output: The test outputs a set of values wrapped in the message published by the laser sensor. These values include respectively: the laser sensor frame ID, the start and end angles of scan, the angular distance between measurements, the time between measurements and scans and the sensor's minimum and maximum range values.

rosrun pepper_diagnostic_routines laser

(g) Test the wheels

Expected output: The tests enable the robot to move forward and backward and perform a clockwise and counterclockwise rotation.

rosrun pepper_diagnostic_routines baseTranslationAndRotation

(h) Test the head control (HeadPitch and HeadYaw)

Expected output: The test moves the head to a predetermined position by following a set of waypoints. This motion generation process relies on the two actuators of the head controller (HeadPitch and HeadYaw) to achieve the desired positioning.

rosrun pepper_diagnostic_routines head_control

(i) Test the left arm (LElbowRoll, LElbowYaw, LElbowYaw, LShoulderRoll and LWristYaw)

Expected output:

The test moves the left arm to a predetermined position, which is specified through a series of waypoints. The motion generation utilizes the five actuators of the left arm controller (LElbowRoll, LElbowYaw, LElbowYaw, LShoulderRoll and LWristYaw) to accomplish this task.

rosrun pepper_diagnostic_routines left_arm_control

(j) Test the left hand

Expected output: The test opens and closes the hand of the Pepper robot. It achieves this by utilizing the actuator of the hand controller (LHand) to perform the required motion.

rosrun pepper_diagnostic_routines left_hand_control

(k) Test the pelvis (HipPitch, HipRoll and KneePitch)

Expected output: The test involves moving the pelvis to a predetermined position by following a set of waypoints. This motion generation process relies on the three actuators of the pelvis controller (HipPitch, HipRoll and KneePitch) to achieve the desired positioning.

rosrun pepper_diagnostic_routines pelvis_control



(l) Test the right arm control (RElbowRoll, RElbowYaw, RShoulderPitch, RShoulderRoll, and RWristYaw)

Expected output: The test moves the right arm to a predetermined position, which is specified through a series of waypoints. The motion generation utilizes the five actuators of the right arm controller (RElbowRoll, RElbowYaw, RElbowYaw, RShoulderRoll and RWristYaw) to accomplish this task.

rosrun pepper_diagnostic_routines right_arm_control

(m) Test the right hand

Expected output: The test opens and closes the hand of the Pepper robot. It achieves this by utilizing the actuator of the hand controller (RHand) to perform the required motion.

rosrun pepper_diagnostic_routines right_hand_control

3.2.1.2 The Pepper Diagnostic Routine Test on the Robot Simulator

In the upcoming version of the document, the execution of the Pepper diagnostic routine test on the Gazebo simulator will be included.

Date: 31/07/2023 Page 16



Principal Contributors

The main authors of this deliverable are as follows (in alphabetical order).

Adedayo Akinade, CMU-Africa Deogratias Amani, CMU-Africa Yohannes Haile, CMU-Africa Mihiretab Taye Hordofa, CMU-Africa Kleber Kabanda, CMU-Africa Natasha Mutangana, CMU-Africa Professor David Vernon, CMU-Africa Pamely Zantou, CMU-Africa

Date: 31/07/2023 Version: No 1.1

Page 17



Document History

Version 1.0

First draft. CSSR4Africa Team. 26 July 2023.

Version 1.1

Fixed several typographical errors.

Updated the Pepper diagnostic routines test on the physical robot to include the expected output of the tests.

Added a new test for the wheels and removed the previous test.

CSSR4Africa Team.

31 July 2023.

Date: 31/07/2023 Page 18